

Upgrading to TSS v11.01 revision F on the PC

1) Download PC version 11.01 revision F from www.spacedesign.com/download.htm

- Unzip the file 'Media.zip'
- Open the 'Media' folder
- Run 'demo32.exe'

2) Perform the TSS installation

- Click 'Install Products'
- Uninstall the old version of TSS
 - o Click the 'TSS and SAT' button
 - o Choose OK to remove TSS
- Install TSS v11.01 revision F
 - o Click the 'TSS and SAT' button (again)
 - o You will be guided through the installation

3) Click the 'License Hostid' button to upgrade your FlexLM License Manager

- The 'Service/License File' tab should be selected
 - o Verify that the 'Configuration Using Services' checkbox is checked
- Select the 'Start/Stop/Reread' tab
 - o If a FLEXnet license server service is listed, click 'Stop Server'
- Select the 'Config Services' tab
 - o Next to the Path to lmgrd.exe, click Browse...
 - Navigate to **C:\Program Files\Space3d\Flexnet Publisher**
 - Highlight 'lmgrd.exe', and select OK
 - o Next to the Path to the license file, click Browse...
 - Navigate to the license file location, which should be in the C:\Program Files\Space3d\Tss\data folder
 - Highlight the *.lic file, and select OK
 - o Make sure the 'use services' and 'start server at power-up' checkboxes are checked
 - o Click 'Save Service'
- Select the 'Start/Stop/Reread' tab
 - o Click 'Start Server'
- Close LMTools

4) If you have a hardware key (dongle), perform the following steps

- Uninstall the current dongle driver
 - o From the Start menu, select Control Panels then Add/Remove Programs
 - o Highlight the current Globetrotter/Flexid driver, and select 'Remove'
- Install the dongle drivers
 - o Run demo32.exe, and select 'Install Products' then 'Dongle Driver'
 - o During the installation, you will have to check the Flexid checkboxes (6/7, 8, 9)
- Re-boot your machine

5) You can now run TSS v11.01 revision F from the Start Menu

- If you previously started the license manager manually (shortcut/Start menu) before running TSS, this is no longer necessary. The service set-up in step 3 will automatically run the license manager each time you start your machine.